

Configuring Windows 98 for Dial Up


Step 1

Go to My Computer then Dial-Up Networking.
Go to Make New Connection.



Step 2

Type Kinect as the Name for the computer you are dialling.
Click Next.



Step 3

Leave the Area code blank
Type the Telephone number as 0867 77770
Select the Country code as New Zealand (64).
Click Next.




Step 4

Click Finish.




Step 5

Click right on your mouse on the icon that says Kinert.
Then click on Properties.




Step 6

Click the tick-box beside Use area code and dialing properties to remove the tick.
Click the Server Types tab up the top.



Step 7

Make sure the following options are ticked:
Enable software compression
TCP/IP.
Click OK.




Step 8

Click right on your mouse on the icon that says Kinect again.

Click on Create Shortcut.

You will get an error saying Windows can not create a shortcut here, would you like it on the desktop instead. Click Yes.



Close down all windows and you will see a Shortcut to Kinect icon on your desktop which can now be used to connect to the Internet.